



SMART PHOTO PRINTER

MODEL

SmartD90 RT/EV


UPDATE REPORT

Version V1.6.0.0



SmartD90 Upgrade procedure

1.- Download the zip file containing V1.6.0 from: <http://www.messec.net> -> Download -> SmartPhotoPrinter



2.- Copy the downloaded “SP_v1600.zip” file in a USB pen drive under the route: **root:// SmartpUpdate/SP_v1600.zip** (Keep Upper and Lower case letters as indicated. Otherwise it won't work).

3.- Switch Off the SmartD90



4.- Attach the USB Pen drive to a free SmartD90 USB port.

5.- . Switch On the SmartD90 and wait until it switch off automatically.



6.- . Switch on and log into the maintenance web and check version

There is no any indication of the upgrade progress, or indication that the upgrade has finished.